




Gmail Integration

This document outlines necessary steps to configure Vaultview Email Integration with Gmail.

Vaultview Settings

1. Login to Vaultview and go to the “Change Email Setting” options




2. Configure your SMTP Email Settings as follows:

Host: smtp.gmail.com	
Port: 587	
Use SSL: Enabled	
Username: Your Gmail User Name	
Password: Your Gmail Password	
Confirm Password: Your Gmail Password	
Email: Your Gmail Email address	

Gmail Settings

1. Login to your Gmail Account.
2. Go to Settings in the upper right corner, select Settings.





3. Select Accounts and Import, then select Other Google Account Settings.

Settings

General Labels Inbox **Accounts and Import** Filters Forwarding and POP/IMAP Chat Labs Offline Themes

Change account settings:
Change password
Change password recovery options
Other Google Account settings

Import mail and contacts:
Learn more
Import from Yahoo!, Hotmail, AOL, or other webmail or POP3 accounts.
Import mail and contacts

Send mail as:
(Use Gmail to send from your other email addresses)
Learn more
Tony Boyer <trontest2015@gmail.com>
Add another email address you own

Check mail from other accounts (using POP3):
Learn more
Add a POP3 mail account you own

Using Gmail for work?
Businesses can power their email with Gmail for Work. Learn more

Grant access to your account:
(Allow others to read and send mail on your behalf)
Learn more
Add another account
 Mark conversation as read when opened by others
 Leave conversation unread when opened by others

Add additional storage:
You are currently using 0 GB (0%) of your 15 GB.
Need more space? Purchase additional storage

4. Select "Connected apps & sites"

My Account

Welcome,


Control, protect, and secure

My Account gives you quick access to the settings and tools that let you safeguard your account and services.

- Sign-in & security**
 - Manage your password and account-access settings.
 - Signing in to Google
 - Device activity & notifications
 - Connected apps & sites
 - Security Checkup
Protect your account in just a few minutes by reviewing your security.
- Personal info**
 - Manage your visibility settings and use to personalize your experience.
 - Your personal info
 - Account history
 - Ads settings
 - Account overview
 - Control your content




5. Turn “Allow less secure apps:” to ON




At this point you should be able to successfully send email from Vaultview through your Gmail Account. Login to Vaultview, retrieve an image and send a test email. You should now receive a message stating that your message has been sent.

6. Log back into Vaultview, retrieve a document and select the email button in the document viewer.





7. The document will be downloaded and the email form opened. Try to send an email.



If your Gmail settings were saved successfully you will get a message stating the email message has been sent.

Contact Information

Support

Email: support@tronitech.com

Phone: 1-800-582-7652

Web: www.tronitech.com/support

Sales

Email: sales@tronitech.com

Phone: 1-800-582-7652